

# **ACME** instructions for TCS-g5 participants

# Create an ACME Enterprise account


An Enterprise Admin can create as many ACME EAB accounts as needed:



When generating the account you only need to select the type of certificates allowed. It's also strongly recommended to set a friendly name, to easily manage ACME accounts:



Finally, it is essential to assign permissions on the organization's pre-validated domains:



There is an option to allow this ACME account to request certificates for all domains. Use it with care.


Add or remove granular rules using + / - symbols preceding domains and rules.

#### **CAUTION**

It's easy to confuse the two blocks for active (green) and inactive (red) rules with blocks for allow (green) and deny (red) rules.

# Handing out credentials

Enterprise Admin can use a secure channel to deliver EAB credentials for the newly created ACME account:



Each ACME account has his own ACME server (there is no single directory for HARICA ACME server).

# Register ACME account

With your preferred ACME client, set the ACME server (directory URL) and register account with EAB credentials given to you.

#### WARNING

Although contact information is optional in the standard, HARICA's ACME server is breaking if you do not provide any email when registering the account

## Request certificates

ACME challenges are not used.

Any request for allowed domains automatically generated the certificate, without the need to demonstrate control (HTTP or DNS) over the domains.


At this time, any request for domains not allowed breaks HARICA's ACME server. You'll get the error Internal Server Error.

#### WARNING

The HARICA ACME server erroneously doesn't accept uppercase characters in DNS names. If they are used, the server generates a **malformed** error

# Managing certificates


Enterprise admins have access to all certificates obtained via ACME, with options to download (both the certificate individually and the complete chain) and revoke:



Big problem: the only way to access one of these certificates in HCM is to enter each ACME account and review all the certificates it has obtained. ACME certificates don't appear in the general list of certificates.

### Personal ACME accounts

Each HCM user can create up to three personal ACME accounts:



Unlike enterprise ACME accounts (created by an Enterprise Admin), personal ACME accounts (created by oneself) imply that it is required to solve ACME challenges in order to get certificates.

Note that an enterprise administrator can also create a personal ACME account. The use of both types of ACME accounts (personal and enterprise) is very different.

Obviously, if you can solve ACME challenges, you'll be able to obtain certificates from many other CA, both free and paid: Let's Encrypt, ZeroSSL (Sectigo), GlobalSign, etc.

The use of ACME personal accounts can be enabled or disabled at the organization level. Its configuration appears in the institution's tags section:

